

Python library for the Radio configuration and status API

The Radio configuration and status API allow users to set configuration parameters and check system status.

The Python library compatible with Python 2.7 and is available in 64-bit version for Linux and 32- and 64-bit versions for Windows.

To use the library you must have "NumPy" installed, see www.numpy.org

- Windows 64-bit: <u>radio_api_lib_win64.zip</u>
- Windows 32-bit: radio api lib win32.zip
- Linux 64-bit: <u>radio_api_lib.tar.gz</u>

Example code that scans the local network for radios and prints wireless status:

```
radio_api_lib.radio = class radio
 Class representing a radio.
  Methods defined here:
   init (self, sn)
        Initializes an instance of the radio class.
        Calculates and sets the MAC and IP address based on the supplied s
        erial number.
        Args:
            sn (int): serial number (also called ID) of unit.
            RadioException
    _repr__(self)
  add_host(self, host_ip, host_mac, desc=None, type_=None, site_id=None, dest_ip=None,
  dest id=None)
        Add a host to this radios host list. Creates a mac-
        ip route on this unit such that the host can talk to other hosts w
        irelessly over the network.
        Devices have to be added to one of the radios on their local netwo
        WARNING: If the host is added, then connected to the local network
         of another site on the same wireless network, it will not be able
         to communicate with the unit on this new site.
            host mac (string): the mac address of the host as a ":" or "-
        " separated string (i.e "aa:bb:cc:dd:aa:bb").
            host ip (string): the ip address of the host as a "." separate
        d string (i.e "1.2.3.4").
            desc (str, optional): description of the host. Shown in the we
        b-gui.
            type_ (str, optional): type description of the host. Shown in
        the web-qui.
            site id (int, optional): if this is set the host will be added
         to the host list of the site with this id.
            dest ip (int, optional): if this is set the host will be added
         to the site list of the radio with this ip.
            dest id (int, optional): if this is set the host will be added
         to the site list of the radio with this id.
        Raises:
            RadioException
  add_site(self, name, radios)
        Add a new site to the site list of the radio.
        Args:
            name (str): the name of the site to be added (i.e "site 1").
            radios (list or int): a list of ids (serial number) of radios
        on the site to be added, or one id as int
        Raises:
            RadioException
  get_frequency(self)
        Get frequency as float
  get_local_site_setup(self)
        Get the local site setup (site name, associated radios and hosts)
        as a dictionary.
  get_network_id(self)
        Get the network id as hex formated long value (i.e 0xaabbccddeeL).
  get_network_superframe_time(self)
        Get superframe time as float
```

```
get_network_time_allocation(self)
      Get current time allocation as a dictionary.
get network time allocation advanced(self)
      Get current advanced time allocation as a dictionary.
get site table(self)
      Get the site table (site names and associated radio serial numbers
      ) as a dictionary.
get_system_status(self)
      Get the system status information as a dictionary.
get_temperature(self)
      Get the internal temperature as float
get_wireless_status(self)
      Get wireless link status information as a dictionary.
init(self, site name=None, radio list=None)
      Initializes the site this radio belongs to with name site name and
       the radios in radio list.
      Args:
          site name (str): name of this site.
          radio list (list of int): the radios on this site.
remove host(self, host ip, host mac)
      Add a host to this radios host list. Creates a mac-
      ip route on this unit such that the host can talk to other hosts w
      irelessly over the network.
      Devices have to be added to one of the radios on their local netwo
      rk.
      WARNING: If the host is added this unit, then connected to the loc
      al network of another site on the same network, it will not be abl
      e to communicate with the units on this new site.
      Aras:
          host mac (string): the mac address of the host as a ":" or "-
      " separated string (i.e "aa:bb:cc:dd:aa:bb").
          host ip (string): the ip address of the host as a "." separate
      d string (i.e "1.2.3.4").
      Raises:
          RadioException
remove_site(self, radio)
      Remove a site from the site list of the radio.
      Args:
          name (str): the name of the site to be added (i.e "site 1").
          radios (list/int): a list of ids (serial numbers as int) of ra
      dios on the site to be added, or one id as int
      Raises:
          RadioException
set datarate(self, mbps)
      Set the transmit datarate.
      Args:
          datarate (int): datarate in Mbps. Valid datarates are 0.5, 1,
      2, 7 and 15 Mbps.
      Raises:
          RadioException
set_frequency(self, mhz)
      Set the radio frequency.
          mhz (float): frequency in MHz. If the supplied value has decim
      als the unit will only use the first two decimals.
      Raises:
          RadioException
set network_id(self, network_id)
```

```
Set the network id.
      Aras:
          network id (int): the network id to be set.
      Raises:
          RadioException
set_network_name(self, network_name)
      Set the network name.
          network name (str or int): the network name to be set.
      Raises:
          RadioException
set_network_time_allocation(self, network_id, superframe_length, allocation)
      Set the network time allocation in a network.
      Args:
          network id (int): the network id of the network.
          superframe length (float): superframe length in milliseconds.
          allocation (dict): dict with serial numbers as int as key and
      allocation percentage as float as value.
                             All radios on the same site share the same
      resource allocation, so only one serial number for each site is ne
      cessary.
                              If the values don't add up to 100%, the res
      t is set as contention period.
                              ex: allocation = \{90: 12.9, 91: 81.1\}
                                  This gives 12.9% to site containing the
       unit with sn 90 and 81.1% to the site containing unit with sn 91.
      Raises:
          RadioException
set_network_time_allocation_advanced(self, superframe_length, time_table)
      Set the network time allocation in a network.
      Args:
          superframe length (float): superframe length in milliseconds.
          time table (dict): dict with serial numbers as int as key and
      desired start of the slot in milliseconds as float as value.
                             All radios on the same site share the same
      resource allocation, so any serial number used on the site will wo
                              Special IDs that can be defined in the key
      are 0 for contention, and 65535 for radio silence.
                              ex: time table = \{90: 0.0, 91: 80.5, 0: 180\}
                                  This gives a slot 80.5 ms slot to site
      containing the unit with sn 90, 99.5 ms to the site containing uni
      t with sn 91, and
                                  20 ms for contention.
      Raises:
          RadioException
set power control(self, max power, target margin, max reduction)
      Sets the power control settings of the radio
```

index

<u>radio_api_lib</u>.radio_api_fu nctions

/home/tob/git/snapgear-2.6-p40-CRE2/python/radio_api_lib/radio_api_fu nctions.py

Modules

binascii ison radio_api_lib.radio_api_lib socket

```
add_host(dest_ip, dest_id, source_id, site_id, macStr, device_ip, desc, type_)
      Adds a new device to the device list of a radio.
          This creates a mac route to a device connected to one of th
      e radios on the network.
          This mac route will be synched between all the radios on th
      e network, and the device
          with mac "device mac" will be available to all other device
      s in the network on
          the ip "device ip".
      Aras:
          dest ip (str): ip of the radio you wish to send the configu
      ration to.
          dest id (int): id (serial number) of the radio you wish to
      send the configuration to.
          source id (int):
                               id of one of the radios on the local si
      te
                                (i.e one of the radios you share a wire
      d network with).
          site id (int): id of one of the radios on the site the devi
      ce is connected to.
          device mac (str): mac of the device
          device ip (str): ip of the device
          desc (str):
                         description of the device
          type_ (str):
                             the type of the device
      Raises:
          RadioException:
add site(dest ip, dest id, source id, name, radio list)
      Adds a new site to the site list of a radio.
      Aras:
          dest ip (str): ip of the radio you wish to send the configu
      ration to.
          dest id (int): id (serial number) of the radio you wish to
      send the configuration to.
          source id (int):
                               id of one of the radios on the local si
      t.e
                                (i.e one of the radios you share a wire
      d network with).
          name (str): the name of the site to be added (i.e "Site 1")
          radio list (list): a list of ids (serial numbers as int) of
       radios on the site to be added.
      Raises:
          RadioException:
get_local_site_setup(dest_ip, dest_id, source_id)
get network time allocation(dest ip, dest id, source id)
get_network_time_allocation_advanced(dest_ip, dest_id, source_id)
get_site_table(dest_ip, dest_id, source_id)
get_system_status(dest_ip, dest_id, source_id)
get_wireless_status(dest_ip, dest_id, source_id)
remove host(dest ip, dest id, source id, macStr, device ip)
```

```
remove_site(dest_ip, dest_id, source_id, site_id)
      Adds a new site to the site list of a radio.
      Args:
          dest ip (str): ip of the radio you wish to send the configu
      ration to.
          dest id (int): id (serial number) of the radio you wish to
      send the configuration to.
          source id (int):
                               id of one of the radios on the local si
      te
                               (i.e one of the radios you share a wire
      d network with).
          name (str): the name of the site to be added (i.e "Site 1")
          radio list (list): a list of ids (serial numbers as int) of
       radios on the site to be added.
      Raises:
          RadioException:
set datarate(dest ip, dest id, source id, datarate)
      Sets the datarate of a Radio
      Args:
          dest ip (str): ip of the radio you wish to send the configu
      ration to.
          dest id (int): id (serial number) of the radio you wish to
      send the configuration to.
          source id (int):
                               id of one of the radios on the local si
      te
                               (i.e one of the radios you share a wire
      d network with).
          datarate (int): datarate in Mbps. Valid datarates are 0.5,
      1,2,7 and 15 Mbps.
      Raises:
          RadioException:
set_frequency(dest_ip, dest_id, source_id, mhz, khz)
      Sets the radio frequency of a Radio
      Args:
          dest ip (str): ip of the radio you wish to send the configu
      ration to.
          dest id (int): id (serial number) of the radio you wish to
      send the configuration to.
          source id (int):
                               id of one of the radios on the local si
      te
                               (i.e one of the radios you share a wire
      d network with).
          mhz (int): mhz part of the frequency
          khz (int): khz part of the frequency
      Raises:
          RadioException:
set network id(dest ip, dest id, source id, network id)
      Sets the network id of a Radio
      Aras:
          dest ip (str): ip of the radio you wish to send the configu
      ration to.
          dest id (int): id (serial number) of the radio you wish to
      send the configuration to.
                               id of one of the radios on the local si
          source id (int):
      t.e
                               (i.e one of the radios you share a wire
      d network with).
          network id (int): the network id to be set
```

```
Raises:
          RadioException:
set_network_name(dest_ip, dest_id, source_id, network_name)
      Sets the network name of a Radio
          dest ip (str): ip of the radio you wish to send the configu
      ration to.
          dest id (int): id (serial number) of the radio you wish to
      send the configuration to.
          source id (int):
                               id of one of the radios on the local si
      te
                               (i.e one of the radios you share a wire
      d network with).
          network name (str): the network name to be set
      Raises:
          RadioException:
set_network_time_allocation(dest_ip, dest_id, source_id, network_id,
superframe_length, allocation)
      Sets the time allocation in a Radio network.
      Args:
          dest ip (str): ip of the radio you wish to send the configu
      ration to.
          dest id (int): id (serial number) of the radio you wish to
      send the configuration to.
                               id of one of the radios on the local si
          source id (int):
      t.e
                               (i.e one of the radios you share a wire
      d network with).
          network id (int): the network id of the network
          superframe length (int): superframe length in miliseconds
          allocation (dict): dict with Radio ids as keys and allocati
      on percentage as values.
                              ex: allocation = \{90: 12, 91: 88\}
                                  This gives 12% to Radio with id 90 a
      nd 88 to Radio with id 91.
      Raises:
          RadioException:
set_network_time_allocation_advanced(dest_ip, dest_id, source_id, network_id,
superframe_length, time_table)
      Sets the time allocation in a Radio network.
      Args:
          dest ip (str): ip of the radio you wish to send the configu
      ration to.
          dest id (int): id (serial number) of the radio you wish to
      send the configuration to.
          source id (int):
                               id of one of the radios on the local si
                               (i.e one of the radios you share a wire
      d network with).
          network id (int): the network id of the network
          superframe_length (int): superframe length in miliseconds
          allocation (dict): dict with Radio ids as keys and allocati
      on percentage as values.
                              ex: allocation = \{90: 12, 91: 88\}
                                  This gives 12% to Radio with id 90 a
      nd 88 to Radio with id 91.
      Raises:
          RadioException:
set_power_control(dest_ip, dest_id, source_id, max_power, target_margin,
max reduction)
```

Modules

radio api lib.radio api lib socket binascii

OS

Classes

exceptions. Exception (exceptions. Base Exception) RadioException

```
class RadioException(<u>exceptions</u>.Exception)
```

Radio Exception class

Method resolution order:

RadioException

exceptions.Exception

exceptions.BaseException

builtin .object

Methods defined here:

```
__init__(self, message)
```

Data descriptors defined here:

```
__weakref
```

list of weak references to the object (if defined)

Data and other attributes inherited from exceptions. Exception:

```
__new__ = <built-in method __new__ of type object>
      T. new (S, ...) -
      > a new object with type S, a subtype of T
```

Methods inherited from <u>exceptions.BaseException</u>:

```
delattr (...)
      x. delattr ('name') <==> del x.name
__getattribute__(...)
      x.__getattribute__('name') <==> x.name
__getitem__(...)
      x. getitem (y) \iff x[y]
__getslice__(...)
      x.<u>getslice</u>(i, j) <==> x[i:j]
      Use of negative indices is not supported.
__reduce__(...)
__repr__(...)
      x.<u>repr</u>() <==> repr(x)
 _setattr__(...)
```

x. setattr ('name', value) <==> x.name = value

```
str (...)
             x.<u>str</u>() <==> str(x)
        unicode (...)
       Data descriptors inherited from <u>exceptions</u>.BaseException:
       dict
       args
       message
discover()
      Discovers all radios on the local network
      Returns:
          list: Containing the serial number of all radios found.
      Raises:
          socket.error
int_to_ip_string(ip)
      Convert ip as in to ip as string
ip_string_to_int(ip_addr)
      Converts an ip as a string to an int
ip_to_sn(ip)
      Convert ip as string to serial number as int
      Returns:
          int: serial number corresponding to the supplied ip.
is_ip(ip_route)
      Checks if a string is a valid ip
is mac(mac)
      Checks if a string is a valid mac
mac_string_to_int(mac)
      Convert a mac address as a "-
      " or ":" separated string to an int
ping(host)
      Returns True if host (str) responds to a ping request. Works fo
      r devices supporting ICMP.
send_buffer(dest_ip, dest_port, datagram, timeout=2)
      Sends a string to ip dest ip at port dest port
      Args:
          dest ip (str): Destination ip as string
          dest port (int): Destination port as int
          datagram (str): String containing the data to be sent
          timeout (int): Socket timeout parameter. Defaults to 2 seco
      nds.
      Raises:
          socket.error
types_ok(arg_list, type_list)
      Checks if a list of arguments are of the correct types specifie
```

setstate (...)

d by a list of types